## Offsets and Water-Use Efficiency MA Smart Growth Conference

**December 1, 2006** 

Duane LeVangie

MassDEP Boston


Bureau of Resource Protection

#### **April 2004 WMA Permitting Policy**

#### Goal: Wise & Balanced Water Use

- More protection of our stressed water resources through implementation of conservation measures
- Reduce nonessential water use
- Apply higher Performance Standards to increases in water use
- Mitigate increases in water use where feasible

#### **Stressed Basins**




- 16 High Stress
- 36 MediumStress
- 18 Low Stress
- Unassessed:mostly coastalbasins

Source: Water Resource Commission stressed basin report (2001) <a href="http://www.mass.gov/dcr/waterSupply/intbasin/stressed\_basins.htm">http://www.mass.gov/dcr/waterSupply/intbasin/stressed\_basins.htm</a>
Based on USGS subbasin stream gages

# Guidance Document for Water Management Act Permitting Policy


- Permit, Permit Amendment Applications, and 5-Year Reviews
  - Guidance # BRP/DWM/DW/G05-01
  - (Supersedes Guidance # BRP/DWM/DW/G04-1)
  - Effective Date: January 17, 2006
- This Guidance applies to all DEP permits issued, modified, or renewed under the Water Management Act on or after the effective date of this Guidance

### **Watershed Urbanization**




## Loss of Groundwater Recharge

#### Stormwater runoff







Infiltration and inflow

## **Growing Water Demands**








#### What are Offsets?

- Measures that return water to the basin or prevent water loss from a basin
- Offsets may include:
  - Stormwater recharge
  - Wastewater return/reuse
  - Infiltration and inflow removal
  - Private well regulation
  - Best Management Practices:
    - Water conservation programs
    - Low Impact Development bylaws
    - Bylaws that regulate land clearing, impervious cover, topsoil, automatic sprinkler systems
    - Source optimization plans
    - Water banking

## Offsetting Withdrawal Increases

- Required in High & Medium Stressed Basins
- Offset Feasibility Study and Implementation
  - (Baseline Use = previous 3 year average, most recent year or registered volume, which ever is higher)
  - High Stress: conduct study after one full year
  - Medium Stress: conduct study after 2nd full year
  - 60 days from ASR submit study scope
  - 6 months from DEP approval of Scope submit Study
  - After 60 days either submittal is presumptively approved
  - Implement Study upon exceedence of baseline in any future ASR

# Reduction of Sewer Inflow and Infiltration



- Fix decaying and broken pipes
- Eliminate roof drain and sump pump connections to sewer
- Repair or replace faulty manhole covers

## Stormwater Management









## Water Re-Use – Municipal Systems

- Use of Treated Sewage Effluent
  - Golf Course Irrigation
  - Municipal Landscaping
  - Water features







## **Low Impact Development**














#### **Baseline**


- Highest of:
  - Registered Volume
  - 3-Yr. (2003-2005)Average WithdrawalVolume
  - 2005 WithdrawalVolume

(in compliance with WMA policy)

 Offsets are required for authorized withdrawals above baseline



#### **Example Baseline Calculation—Town in Multiple Basins**



## Offset Requirement Volume


#### Based on

- Authorized withdrawal volume in excess of baseline
- Summer to winter water use ratio
- Percent of town on sewer or septic system
- Location of discharge points

#### Assumptions

- Difference between summer water use and winter water use is due to outside uses
- 75 % of outside water use in summer is lost to evapotranspiration (ET)
- Sewer systems: all indoor water use and outside water lost to ET must be offset
- Septic systems: all outside water lost to ET must be offset

## Offset Requirement Volume



#### **Offset Credits**

- Offset credit is applied toward the reduction of the offset requirement volume
- Potential "measurable" credits:
  - Private well regulation
  - Infiltration and inflow (I/I) reduction
  - Stormwater recharge
- To receive proper credit, each practice must be feasible for the town to implement

## Offset Credit: Private Well Regulation

#### Private well offset calculated from:

- Summer and winter water use
- Number of service connections reported in ASR
- Number of private wells

#### Assumptions:

- Reduction in summer use by 20% (winter use assumed the same)
- Private well use is same as public supply

#### Calculation:

Based on 2001-2003 ASR data for 14 towns:

Avg savings/well = 33 GPD


Minimum = 23 GPD

Maximum = 42 GPD

#### Problems with accounting approach:

- Don't know actual use volumes or patterns
- Difficulty in regulating—meter wells? How to enforce?

## Offset Credit-Private Well Regulation



#### Offset Credit: Inflow and Infiltration Reduction

#### Background:

- MWRA estimates of I/I for 1998, 2002, 2003 cover wide range
  - Inflow ranged from 3 to 29 % of avg. daily sewer flow
  - Infiltration ranged from 17 to 68 % of avg. daily sewer flow

#### Problems with accounting for I/I:

- Difficult to measure I/I and estimate potential offset reductions
- Highly variable, depending on
  - Location (proximity to wetlands, low-lying areas)
  - Age of system
  - Storm events
  - Soil types
- What is an achievable offset goal—minimum from a group of towns, average, 20 % reduction?
- Time frame for achieving goal (one year?, 5 years?, 10 years?)

## Summary

- Current WMA guidance document requires offset feasibility study to be conducted when withdrawals exceed baseline
- Offset requirement volume determined from withdrawals in excess of baseline, summer to winter water use, percent sewered/septic, and location of discharge points
- Accounting approach would assign credits to BMPs and other practices with goal of reducing offset requirement volume to zero
- Alternative approach? Implement a number of BMPs without tracking credits